



Users manual Configuration of GOL

Version 1.0

Content

1	Getting started with GOL	5
1.1	Access conditions	5
1.2	Access GOL	5
2	Finishing the work with GOL	7
3	GOL configuration sections	8
3.1	Configuration of GOL settings	9
3.2	Configuration of user profile	9
3.3	Change of user password	11
3.4	Configuration of golLoader agents	12
3.4.1	Hosts tab	12
3.4.2	New hosts tab	14
3.4.3	Removed hosts tab	15
3.4.4	golLoader configuration window	16
3.4.5	Configuration of golLoader general settings	21
3.4.6	Configuration of log data file settings	22
3.4.7	Deleting of log file from the list	25
3.4.8	Connection of a new log file to the golLoader	25
3.5	Alert configuration	26
3.5.1	Configuration of alert settings	28
3.6	Dashboard configuration	30
3.7	Configuration of GOL general settings	34
3.7.1	Description of General tab settings	34
3.7.2	Description of Storages tab settings	34
3.8	Configuration of GOL users	37
3.8.1	GOL user types and rights	38
3.8.2	Adding of new GOL user	38
3.8.3	Change of user settings and deleting of users	39

List of pictures

Picture 1. GOL access form.....	5
Picture 2. Warning about incorrectly entered username or password.....	6
Picture 3. GOL configuration items.	8
Picture 4. User profile settings window.	9
Picture 5. Window with user settings.	11
Picture 6. Window with the list of connected agents.	12
Picture 7. Dialog for confirmation of golLoader deleting.....	13
Picture 8. Window wit the list of new golLoader agents.	14
Picture 9. Window with the list of deleted golLoader agents.	15
Picture 10. golLoader configuration window.	16
Picture 11. Example with log file entries in New sources tab.	19
Picture 12. Example with list of log files in the Removed sources tab.	20
Picture 13. Window for configuration of golLoader general settings.	21
Picture 14. Log file configuration window.	23
Picture 15. Log file list example with disabled log file in Sources tab.	24
Picture 16. Log file deleting dialog window.	25
Picture 17. Window for alerts list.	26
Picture 18. Alert configuration window.	26
Picture 19. Example of list with alerts.	27
Picture 20. Window with alert settings information.	28
Picture 21. Alert deleting confirmation window.	29
Picture 22. Windows for list of dashboards.....	30
Picture 23. Window for configuration of dashboard name.	30
Picture 24. Window for the list of dashboard queries.	31
Picture 25. Window for configuration of a dashboard query.....	31
Picture 26. Example with list of queries.	32
Picture 27. Example with list of dashboards.	33
Picture 28. GOL general settings configuration window.....	34
Picture 29. golDB settings window.	35
Picture 31. Example with list of GOL users.....	37
Picture 32. Using settings configuration window.	38
Picture 33. Summary of user settings.	39
Picture 34. Dialog for confirmation of user deletion.....	40
Picture 35. List with deleted users.	40

List of tables

<i>Table 1. Description of GOL configuration items.</i>	<i>8</i>
<i>Table 2. User profile configuration settings.</i>	<i>9</i>
<i>Table 3. Description of user settings.</i>	<i>11</i>
<i>Table 4. Description of the columns in Hosts tab.</i>	<i>12</i>
<i>Table 5. Description of columns in New hosts tab.</i>	<i>14</i>
<i>Table 6. Description of columns in Removed hosts tab.</i>	<i>15</i>
<i>Table 7. Description of fields in agents configuration window.</i>	<i>16</i>
<i>Table 8. Description of columns in Sources tab.</i>	<i>17</i>
<i>Table 9. Description of items in the New sources tab.</i>	<i>19</i>
<i>Table 10. Description of columns in the Removed sources tab.</i>	<i>20</i>
<i>Table 11. Description of the fields in configuration window.</i>	<i>22</i>
<i>Table 12. Description of fields in log file configuration window.</i>	<i>23</i>
<i>Table 13. Description of alerts settings.</i>	<i>27</i>
<i>Table 14. Description of the positions in the list of alerts.</i>	<i>28</i>
<i>Table 15. Description of fields in dashboard name configuration window.</i>	<i>30</i>
<i>Table 16. Description of the dashboard configuration fields.</i>	<i>31</i>
<i>Table 17. Description of the dashboard fields.</i>	<i>32</i>
<i>Table 18. Description of the columns in the list of queries.</i>	<i>32</i>
<i>Table 19. Description of columns in the list of dashboards.</i>	<i>33</i>
<i>Table 20. Description of configuration tabs.</i>	<i>34</i>
<i>Table 21. Description of settings in the General tab.</i>	<i>34</i>
<i>Table 22. Description of golDB database settings.</i>	<i>35</i>
<i>Table 24. Description of columns in the users list.</i>	<i>37</i>
<i>Table 25. Configuration rights available to each user type.</i>	<i>38</i>
<i>Table 26. Description of user settings.</i>	<i>38</i>
<i>Table 27. Description of items in user summary window.</i>	<i>39</i>

1 Getting started with GOL

Work with the GOL can start only registered user and to act in accordance with the rights granted to the user.

1.1 Access conditions


GOL is available to all users, but user can only act according to the assigned rights. New users can be created only by user with administrator rights.

Role: *Administrator* is available by default. Additional role levels: *User* and *Manager* can be granted to the user only by Administrator.

In order to carry out its functions in accordance with the role assigned to a user authentication system must have the necessary information - username and password. More about GOL user creation is described in the chapter 3.8 *Configuration of GOL users*.

1.2 Access GOL

To get started with GOL in internet browser command line enter „*http://[IP]/gol/*“.Where [IP] indicates the server address on which GOL is installed. GOL-GUI access form opens (**Error! Reference source not found.**).




Picture 1. GOL access form.

To start GOL configuration it should be accessed with Administrator rights. GOL installation already had set up default Administrator login and password:

Username: admin


Password: password


The username must be written in the field with  icon, but password in the field with  icon. Press **LOGIN** button.

The GOL-GUI work screen opens and the user can start working according to the rights granted.

The access rights with which the user has accessed the GOL are shown on menu line - **Logged in:**. For example, user with Administration rights will be displayed as "admin":

Logged in: admin


If an incorrect user name or password has been entered warning will be displayed (*Picture 2*), which after a few seconds will be shut by himself. Warning message can be closed by pressing icon .



Picture 2. Warning about incorrectly entered username or password.


REMARK! It is recommended to change default administrators name and password.

2 Finishing the work with GOL

To finish and log out from GOL-GUI at the end of menu line icon  could be pressed. GOL-GUI access form opens again and tab in internet browser can be closed.

3 GOL configuration sections

GOL configuration items are available in main menu position **Configuration**. Window with configuration items will be opened (*Picture 3*).



Picture 3. GOL configuration items.


In the configuration window GOL configuration items are shown, by clicking on the icon  an explanation of each configuration item is available. Description of each GOL configuration item is available in *Table 1*.

Table 1. Description of GOL configuration items.

Item	Description
My profile	In this section, general user settings can be viewed and changed, such as the main screen that opens after authorization in the system etc. Described in chapter3.2 <i>Configuration of user profile</i> .
Change password	Section for changing username and password. Described in chapter3.3 <i>Change of user password</i> .
Hosts	In this section all attached to GOL devices can be viewed and configured golLoaders. Described in chapter3.4.4 <i>golLoader configuration window</i>
Alerts	Section for alert configuration and management. Described in chapter3.5 <i>Alert configuration</i> .
Dashboards	Section for configuration and management of dashboards. Described in chapter3.6 <i>Dashboard configuration</i>
General	Section for configuration of GOL general settings, such as change of systems name, definition of e-mail for system alerts, golDB and other settings. Described in chapter3.7 <i>Configuration of GOL general settings</i>
Users	Section for user definition and configuration. Described in chapter3.8 <i>Configuration of GOL users</i> .

3.1 Configuration of GOL settings

To access the corresponding section for configuration of settings click on the appropriate title name in the GOL configuration window (Picture 3).

3.2 Configuration of user profile

In order to change GOL user profile settings click on the **My Profile** section (Picture 3). User profile settings window will be opened (Picture 4).

Picture 4. User profile settings window.

Description of user settings is available in Table 2.

Table 2. User profile configuration settings.

Name of the field	Description
System settings	<p>From the dropdown menu Default page can be set the screen that will be shown as first after login:</p> <ul style="list-style-type: none"> • <i>Summary</i>: screen with network chart; • <i>Filters</i>: screen with list of saved search queries; • <i>Dashboards</i>: screen with list of dashboards; • <i>Alerts</i>: screen with list of alerts; • <i>Configuration</i>: screen with configuration setup window.
Search settings	<ul style="list-style-type: none"> • In the input field Results per page can be set the amount of log entries visible on screen. • Switch Show time chart indicates status of time chart – visible/hidden. By default time chart is visible. • Switch Show side menu indicates the status of window with structured information – visible/hidden. By default the window is visible.

	<ul style="list-style-type: none">• In the dropdown menu Search result view can be set the way how the search results will be displayed - with or without information about the data source:<ul style="list-style-type: none">▪ <i>Simple</i> – results without information about data source. Default setting;▪ <i>Labels</i> – results with information about data source.
--	--

3.3 Change of user password

In order to change user password in the window with GOL settings items (*Picture 3*) press **Change password**. Window with user settings will be opened (*Picture 5*).

Picture 5. Window with user settings.

Description of input fields is available in *Table 3*.

Table 3. Description of user settings.


Field	Description
Name	Displays user name. Cannot be change.
Description	Displays description of the user. Cannot be changed.
Level	Displays the access level set to user. Cannot be changed.
E-mail	Displays user's e-mail address. Cannot be changed.
Old password	User's old password.
New password	User's new password. Password should be at least 6 symbols long.

In order to change user's password in the field **Old password** old password must be written, but in the field **New password** write user's new password. To save the changes button **Save** must be pressed. GOL will return to the login window (*Picture 1*), where user name and new password can be entered.

3.4 Configuration of golLoader agents

This chapter describes the overall golLoader agent configuration and change of the settings using the GOL-GUI. golLoader configuration during installation is described in document „Users manual. GOL installation“.

In order to change golLoader settings in the window with GOL settings items (*Picture 3*) press **Hosts**. The window with list of agents connected to golDB will be opened (*Picture 6*).



Picture 6. Window with the list of connected agents.

The list of agents has several tabs:

- **Hosts (x)**. Tab with the list of all agents connected to golDB;
- **New hosts (x)**. Tab with list of new agents that need configuration and activation;
- **Removed hosts (x)**. Tab with deleted agents.







Index **(x)** displays the amount of the entries in each list. Search for agent by its name or description is available. In order to find agent in the field start typing the name and in the time of writing, GOL will start to display entries relevant to the typed part of the word.

3.4.1 Hosts tab








Description of columns in the tab **Hosts** (*Picture 6*) is available in *Table 4*.


Table 4. Description of the columns in **Hosts** tab.

Column	Description
Indicator	<p>Indicate the status of the agent. Possible icons and meaning of the indicator:</p> <ul style="list-style-type: none"> • indicates that golLoader is active and sending data to golDB; • indicates that golLoader is activated but not sending the data to golDB;

	<ul style="list-style-type: none">  indicates that golLoader is inactive (disabled).
Name	Name of the golLoader.
Code	golLoader code with which it is identified in goDB. This code can be used for building of search queries.
Description	Description of the golLoader.
Enable	Switch for enabling or disabling of golLoader. Possible positions of the switch: <ul style="list-style-type: none"> Position  indicates that golLoader is enabled; Position  indicates that golLoader is disabled; Position of the switch can be changed by pressing on its icon.
Edit	Icon  for opening of golLoader configuration window.
Remove	Icon  for deleting of the golLoader from the list.
	Icon for adding of a new golLoader.

With golLoader in **Hosts** tab (*Picture 6*) can be performed following operations:

- **Opening of golLoader configuration window.** Described in chapter 3.4.4 *golLoader configuration window*;
- **Enabling or disabling of golLoader.** In normal situation golLoader in **Hosts** tab is enabled and switch is in position . In same time icon before the name is , if the data are sent to goDB or , if the golLoader is not sending the data. In order to disable the golLoader the switch must be moved to position . In this case icon before the name will be changed to . In order to activate golLoader again switch must be moved to position .
- **Deleting of golLoader from the list.** In order to delete golLoader from the list in **Hosts** tab icon  must be pressed. The dialog for confirmation of deleting will be opened (*Picture 7*).



Picture 7. Dialog for confirmation of golLoader deleting.

In order to confirm deleting of golLoader the **OK** button must be pressed. Pressing the **Cancel** button will cancel deleting request. Agent will be moved to **Removed hosts** tab.

- **Adding of a new agent.** Described in document „Users manual. GOL installation“.

3.4.2 New hosts tab






In the tab **New hosts** (Picture 8) the list with new agents that should be configured and enabled is available. Enabling process is described in document „Users manual. GOL installation“.




Picture 8. Window with the list of new golLoader agents.


The description of columns in **New hosts** tab is available in Table 5:

Table 5. Description of columns in **New hosts** tab.

Column	Description
Indicator	Indicates the status of the agent. Icon  indicates that agent is not activated.
Name	Name of the agent.
Code	For new agents that are not activated yet this field is empty.
Description	Description of agent.
Enable	Sign  indicates that agent is new and not configured yet.
Edit	Icon  for opening of golLoader configuration window.
Remove	Icon  for deleting of golLoader from the list.
	Icon for adding of a new agent.

With golLoader in **New hosts** tab (Picture 8) can be performed following operations:

- **Opening of golLoader configuration window.** Described in chapter 3.4.4 *golLoader configuration window*;
- **Deleting of golLoader from the list.** In order to delete golLoader from the list in **Hosts** tab icon  must be pressed. The dialog for confirmation of deleting will be opened (Picture 7). Deleted golLoader will be moved to **Removed hosts** tab.

- **Adding of a new agent.** In order to add a new agent icon  must be pressed. Operations for adding a new agent are described in the document „Users manual. GOL installation“.

3.4.3 Removed hosts tab




In the **Removed hosts** tab (*Picture 9*) the list with deleted agents is displayed. Deleted agents can be activated again.



Picture 9. Window with the list of deleted golLoader agents.

The description of columns in **Removed hosts** tab is available in *Table 6*.


*Table 6. Description of columns in **Removed hosts** tab.*


Column	Description
Indicator	Indicates status of the agent. Icon  indicates that agent is not activated.
Name	Name of the agent.
Code	For deleted agents this field is empty.
Description	Description of agent.
Enable	Sign  indicates that agent is deleted.
Edit	Icon  for opening of golLoader configuration window.

With golLoader in **Removed hosts** tab (*Picture 9*) can be performed following operations:

- **Opening of golLoader configuration window.** If the golLoader should be activated again than that can be done as described in chapter 3.4.4 *golLoader configuration window*. After activation golLoader will be displayed in **Hosts** tab again.

3.4.4 golLoader configuration window




By pressing on icon  in the **Hosts**, **New hosts** and **Removed hosts** tabs the golLoader configuration window will be opened (*Picture 10*).








Picture 10. golLoader configuration window.


In the configuration window the information about golLoader is displayed with the possibility to enable or disable it with switch and opening the window for configuration of general settings. The list with log data sources connected to the agent is available as well. Description of the fields in agent's configuration window is available in *Table 7*.

Table 7. Description of fields in golLoader configuration window.

Field	Description
Switch	Switch for enabling or disabling of golLoader. Possible positions of the switch: <ul style="list-style-type: none"> Position  indicates that golLoader is enabled; Position  indicates that golLoader is disabled; Position of the switch can be changed by pressing on its icon.
	Icon for opening of the window for configuration of golLoader general settings.
Tabs Sources , New sources , Removed sources	Lists with log data sources connected to the golLoader according their statuses.

For configuration of golLoader following operations are available:

- Enabling or disabling of golLoader.** In order to disable the golLoader switch icon  must be pressed (*Picture 10*). It will be changed to , but the indicator before the golLoader name in **Hosts** tab will be . In order to enable the golLoader again icon  must be pressed and icon in the **Hosts** tab (*Picture 6*) will be changed to  accordingly. If the golLoader is enabled but not sending data to

database than indicator in **Hosts** tab will be . By enabling the agent in **New hosts** and **Removed hosts** tabs it will be moved to **Hosts** tab.

- **Configuration of golLoader general settings.** Described in chapter 3.4.5 *Configuration of golLoader general settings.*

golLoader configuration window has several tabs with lists of log data sources connected to it (**Picture 10**):

- **Sources (x)** tab contains a list of log data sources from which the entries are sent to golDB;
- **New sources (x)** tab contains a list of log data sources that has been automatically recognized by golLoader;
- **Removed sources (x)** tab contains log data sources that have been deleted from **Sources** and **New sources** tabs.

Index **(x)** indicates the amount of entries in each list.




Search for log data source by its name or description is available in all tabs. In order to find






log data source in the field start typing the name and in the time of writing, GOL will start to display entries relevant to the typed part of the word.

3.4.4.1 golLoader configuration window Sources tab

Sources tab (*Picture 10*) contains a list of log data sources from which the records are sent to golDB. Description of columns in **Sources** tab is available in *Table 8*.

Table 8. Description of columns in **Sources** tab.

Column	Description
Indicator	Indicates the status of log data source. Possible icons of the indicator: <ul style="list-style-type: none"> •  indicates that log data transfer is active; •  indicates that log data source is enabled but data are not sent to golDB; •  indicates that log data sending is disabled.
Name	Name of log data source.
Code	Code with which log data source is identified in golDB. This code can be used for building of search queries.
Description	Description of log data source.
Type	Indicates the type of log data. Current version of GOL supports following log data types: <ul style="list-style-type: none"> • LC (load custom) - data type for sources which structure is not described in golDB; • SNMP trap - log data type for data received from SNMP trap; • CPS2 - data type for golDB and Clusterpoint database logs; • Windows Events - data type for MS Windows event logs;


	<ul style="list-style-type: none"> • Apache2 error – data type for Apache server error logs; • Apache2 access – data type for Apache server access logs; • Syslog – data type for Linux system logs.
File	Fixed part of the log file name.
Storage	golDB instance to which the log data are sent.
Enable	<p>Switch for enabling or disabling of log data sending from particular log data source. Possible positions of the switch:</p> <ul style="list-style-type: none"> • Position  indicates that log data transmission is enabled; • Position  indicates that transmission of log data is disabled. <p>Position of the switch can be changed by pressing on it.</p>
Edit	Icon  for opening of window for configuration of log data transmission settings.
Remove	Icon  for deleting of log data source from the list.
	Icon for adding of a new log data source.

Following operations can be performed with the entries in the **Sources** tab:

- **Enabling or disabling of data transmission from particular data file.** Described in the chapter3.4.4.4 *Enabling and disabling of log data transmission*.
- **Configuration of the log data files settings.** Described in the chapter3.4.6 *Configuration of log data file settings*.
- **Deleting of log files from the list.** Described in the chapter3.4.7 *Deleting of log file from the list*.
- **Attaching of a new log data file to the golLoader.** Described in the chapter3.4.8 *Connection of a new log file to the golLoader*.

3.4.4.2 golLoader configuration window **New sources** tab

In the **New sources** tab entries appear only after installation of golLoader on the host and automatic recognition of log files. If the list after golLoader installation is empty than log files must be attached manually as described in the chapter 3.4.8 *Connection of a new log file to the golLoader*. Example with entries in **New sources** tab is available in the *Picture 11*.



Picture 11. Example with log file entries in **New sources** tab.

Description of items in **New sources** tab is available in *Table 9*.

Table 9. Description of items in the **New sources** tab.

Item	Description
Indicator	Icon indicates that log data transmission is not enabled and it should be configured.
Name	The name of log data file that has been automatically detected by golLoader. It can be changed if necessary.
Code	Code with which log data source is identified in golDB and will be used after activation of data transmission.
Description	Description of log file. By default it is empty.
Type	Indicates the type of recognized log file.
File	Fixed part of the log file name.
Storage	golDB instance to which the log data will be sent. By default – main .
Enable	Sign indicates that log data source is not configured yet.
Edit	Icon for opening of log data source settings configuration window.
Remove	Icon for deleting of log data source file from the list.
	Icon for adding of a new log data file to the list.

With entries in the **New sources** tab following operations can be performed:

- **Configuration of settings of log data file.** Described in the chapter 3.4.6 *Configuration of log data file settings.*
- **Deleting of the log files from the list.** Described in the chapter 3.4.7 *Deleting of log file from the list.*
- **Adding of a new log data source to the list.** Described in the chapter 3.4.8 *Connection of a new log file to the golLoader.*

3.4.4.3 golLoader configuration window Removed sources tab




In the **Removed sources** tab log files appear after deleting from **Sources** and **New sources** tabs. Example of list in the **Removed sources** tab is available in the *Picture 12.*



Picture 12. Example with list of log files in the **Removed sources** tab.

Description of columns in the **Removed sources** tab is available in the *Table 10.*









Table 10. Description of columns in the **Removed sources** tab.

Columns	Description
Indicator	Icon  indicates that log data transmission is disabled, but it can be enabled again by changing of log file status.
Name	Name of the log data file.
Code	Code with which log data source is identified in golDB.
Description	Description of log data file.
Type	Type of log data.
File	Fixed part of the log file name.
Storage	golDB instance to which the log data were sent. By default – main .
Enable	Sign  indicates that particular log data file is removed from the list.
Edit	Icon  for opening of the log data source configuration window.


With entries in the **Removed sources** tab following operations can be performed:


- **Configurations of the log file settings for its activation.** Described in the chapter 3.4.6 *Configuration of log data file settings.*

3.4.4.4 Enabling and disabling of log data transmission

Enabling and disabling of the log data sources can be performed in the **Sources** tab. In order to enable the data transmission from the log file with icon  before its name the switch  must be pressed. Switch icon will be changed to  and the transmission of log data will be enabled and status icon before the log file name will be changed to . In case if log data are not sent the status indicator will be . In order to disable the log data transmission switch icon  must be pressed, icon will be changed to , but status icon will change to .

3.4.5 Configuration of golLoader general settings

In order to perform configuration of golLoader general settings the configuration window must be opened by pressing on icon  at the end of the line with golLoader name (*Picture 10*). The window for configuration of the golLoader general settings will be opened (*Picture 13*).






The screenshot shows a configuration window titled "Edit host" with a help icon and a "Back to host" link. The window contains several input fields and a "Save" button. The fields are:

- Code: h_1
- Name: golDB
- Description: GOL host
- Pool count: 200
- Sleep time (s): 10
- Enable loading files from this host:
- Link to a new loader: No new loaders

Picture 13. Window for configuration of golLoader general settings.

Description of fields in configuration window is available in *Table 11*.


Table 11. Description of the fields in configuration window.

Field	Description
Code	Code with which golLoader is identified in golDB.
Name	Name of the golLoader.
Description	Description of the golLoader.
Pool count	The amount of log entries which golLoader is sending to golDB during each session. By default maximum 200 entries will be sent.
Sleep time (s)	The interval in seconds between each session can be specified. By default interval is set to 20 seconds.
Enable loading files from this host:	Switch for enabling or disabling of golLoader. Possible positions of the switch: <ul style="list-style-type: none"> • Position  indicates that golLoader is enabled; • Position  indicates that golLoader is disabled. Position of the switch can be changed by pressing on it.
Link to a new loader	Dropdown menu for attachment of golLoader to golDB. In normal case the golLoader already is attached and sign „No new loaders” will be visible. This option should be used in cases when is necessary to restore previously deleted golLoader.
	Button for saving of configuration.

In golLoader configuration window following operations can be performed:

- Changing of golLoader name in the **Name** field;
- Changing of golLoader description in the **Description** field;
- Changing of the amount of log entries in the field **Pool count**;
- Changing of the interval in seconds between each data transmission session in the **Sleep time (s)** field. This parameter should be aligned with **Pool count** and growth rate of entries in log file. If **Pool count** will be small and time interval large, the situation may arise where the freshest of log entries in the database will arrive with delay.

3.4.6 Configuration of log data file settings

In order to configure log file settings in the tabs **Sources**, **New sources** and **Removed sources** the icon  must be pressed. The log file configuration window will be opened (Picture 14).

Edit source Back to host

Host:

Source name:

Description:

Type:

Storage:

Load previous logs:

Enable load this source files:





File directory:





File name:

Picture 14. Log file configuration window.

Description of fields in log file configuration window is available in *Table 12*.

Table 12. Description of fields in log file configuration window.



Field	Description
Host	Name of the device from which the log data are sent. Cannot be changed.
Source name	Name of the log data source.
Description	Description of the log data source.
Type	Type of log data. Type can be selected from dropdown menu by pressing on icon  . Available log data types described in <i>Table 8</i> .
Storage	Indicates the database instance where log data are stored. Instance can be selected from dropdown menu by pressing on icon  . By default GOL has only one instance - main .
Load previous logs	Switch for enabling or disabling of historical log data sending. Possible positions of the switch: <ul style="list-style-type: none"> Position  indicates that sending of historical data is enabled; Position  indicates that sending of historical log data is disabled. Switch position can be changed by pressing on its icon.


Enable load this source files	Switch for enabling or disabling of log data sending from log file. Possible positions of the switch: <ul style="list-style-type: none"> Position  indicates that log data sending from file is enabled; Position  indicates that log data sending from file is disabled. Switch position can be changed by pressing on its icon.
File directory	Indicates the folder which contains log file.
File name	Name of unchanging part of log file.
	By pressing Duplicate button the new configuration will be generated with current settings.
	Button for saving of configuration.
















In log file configuration window following operations can be performed:

- Changing of log file name in **Name** field;
- Changing of log file description in **Description** field;
- Enabling or disabling of log data sending by changing the switch position in **Enable load this source files** and **Load previous logs** field;

Changes to other settings are not recommended because that can lead to incorrect work of golLoader.


In case when log data transmission is disabled in **Enable load this source files** field, in the tab **Sources** before the appropriate file name icon  will appear. It indicates that the log data sending is disabled. At the same time the switch in column **Enable** will be in the position . Example is shown in the *Picture 15*.




Name	Code	Description	Type	File	Alias	Storage	Enable	Edit	Remove
Messages	h_1_src_1		syslog	messages	main				
Syslog	h_1_src_2		syslog	syslog	main				
User	h_1_src_3		syslog	user	main				
Apache access	h_1_src_4	Apache 2 access log	apache2acc	access.log	main				
Apache error	h_1_src_5	Apache 2 error log	apache2err	error.log	main				

Picture 15. Log file list example with disabled log file in **Sources** tab.

3.4.7 Deleting of log file from the list


Log file in **Sources** and **New sources tab** can be deleted by pressing on icon  in the column **Remove** (*Picture 15*). The window with dialog for confirmation of deletion will be opened (*Picture 16*). To confirm the deletion button **OK** must be pressed. Appropriate log file will be moved to **Removed sources** tab. Log file can be activated again as described in the chapter *3.4.4.4 Enabling and disabling of log data transmission*.



REMARK! The log files on disk and entries in the database are not affected.



Picture 16. Log file deleting dialog window.


3.4.8 Connection of a new log file to the goLoader

A new log file can be added to the list in the **Sources** and **New sources** tabs by pressing icon  in the goLoader configuration window (*Picture 14*). In the window following fields must be filled (described in *Table 12*):


- **Source name:** A short name of log file must be entered;
- **Description:** Description of log file can be written optionally;
- **Type:** The appropriate to log data type must be chosen from dropdown menu;
- **Storage:** The database instance where log data will be stored must be chosen from dropdown menu. By default there will be available only one instance – **main**;
- **File directory:** Full path on disk where log file is located must be written;
- **File name:** The unchanging part of log file name must be written. This is necessary for automatic recognition of rotation files with historical log entries. If data type **Load custom** is used and the historical information is needed as well the file name can be specified as regular expression. For example, expression `/^ERRORLOG([.][0-9]{1,5}){0,1}$/` specifies the **MySQL error log** file. How to build a regular expression can be viewed in <http://regexone.com>;
- **Load previous logs:** Optionally the loading of historical log entries can be disabled by pressing on switch icon. By default switch is in position , indicating that historical data loading is enabled;
- **Enable load this source files:** The goLoader can be disabled by pressing on the switch icon. By default switch is in position , indicating that goLoader is enabled and log data loading will start (or to be continued) after saving of configuration.


3.5 Alert configuration

In order to configure alerts, in the configuration window (*Picture 3*) the item **Alerts** must be chosen. The window for list of alerts will be opened (*Picture 17*). Initially the list is empty.



Picture 17. Window for list of alerts.

In order to create new alert the icon  must be pressed. The alert configuration window will be opened (*Picture 18*).


The image shows a "New Alert" configuration window with a help icon and a "Back to alerts" link. The form is divided into two columns. The left column contains: "Name:" with a text input; "Description:" with a larger text area; "Query:" with a larger text area; "Interval (s):" with a text input; "Max count:" with a text input; and "Level:" with a dropdown menu currently set to "Low". The right column contains: "Send E-mails:" with a checked toggle switch; "E-mails:" with a text area; "Show popup:" with a checked toggle switch; "Expire after (days):" with a text input containing "365"; "Enable alert:" with a checked toggle switch; and "Filter previous logs:" with an unchecked toggle switch. At the bottom right of the window is a blue "Save" button.


Picture 18. Alert configuration window.

Description of alert settings is available in *Table 13*.

Table 13. Description of alerts settings.

Field	Description
Name	Short name of an alert. It will be shown in the column Name and will be used for identification of triggered alerts.
Description	Description of an alert for identification of purpose the alert is serving. Entry will be shown in the Description column.
Query	Query for identification of event for alert triggering. Entry will be shown in the Filter column. Queries can be prepared in the search field and then copied to the settings field.
Interval (s)	Time interval in sec. in which the query will be searched.
Max count	Amount of quires found in the time interval for triggering of an alert.
Level	Dropdown menu for assigning of the importance level to the alert. Available levels are: <ul style="list-style-type: none"> • Low; • Moderate; • High; • Urgent.
Send E-mails	Switch for enabling of e-mail transmission if alert is triggered. By default switch is in position - enabled.
E-mails	E-mail addresses to which the information about the alert must be sent. Multiple e-mail addresses can be specified by separating one from another with „,“.
Show popup	Switch for enabling of alert displaying in the pop-up window.
Expire after (days)	Identifies after how many days alert will be automatically removed from the list.
Enable alert	Switch for enabling or disabling of the alert. By default switch is in position – enabled.
Filter previous logs	Switch for enabling of search for alert in the historical logs. By default switch is in position – disabled.

In order to save the configuration button  must be pressed. GOL-GUI will return to the list of prepared alerts. Example is shown in the *Picture 19*.







Name	Description	Filter	Level	Status	Edit	Remove
Demo alert	Just simple demo	Filter: (:server==h_1 ALERT) Max 1 records in 30 seconds.	Low	Last executed on 2014/03/21 12:28:09		

Picture 19. Example of list with alerts.

Description of the positions in the list of alerts is available in *Table 14*.

Table 14. Description of the positions in the list of alerts.

Position	Description
Name	Short name of the alert.
Description	Description of the alert.
Filter	Query for triggering of the alert. Additionally the time interval and amount of query triggers specified as well.
Level	Importance level assigned to the alert.
Status	Time and date of last time when alert was triggered.
Switch	Switch icon  identifies that alert is enabled. Switch icon  indicates that alert is disabled.
Edit	Icon  for opening of the alert configuration window (<i>Picture 6.</i>).
Remove	Icon  for deleting of alert from the list.


3.5.1 Configuration of alert settings

Alert settings can be configured in following ways:


- By clicking on the alerts name in column **Name**;
- By clicking on icon  in column **Edit**.

3.5.1.1 Alert settings configuration by clicking on the name


By clicking on the alert name in the **Name** column the window with alert settings information will be opened (*Picture 20*).




Picture 20. Window with alert settings information.


Pressing on icon  in the alert information window for alert configuration will be opened (*Picture 18*). Clicking on **Back to alerts** sign or button **Back** GOL-GUI will return to the list of alerts.

3.5.1.2 Alert settings configuration by clicking the edit icon

If it's not necessary to overview the summary of alert settings than icon  can be pressed immediately.

3.5.1.3 Deleting of alert from the list

Alert can be deleted by clicking the  icon (*Picture 19*). The dialog for confirmation of deleting will be opened (*Picture 21*).




Picture 21. Alert deleting confirmation window.

In order to confirm alert deleting the **OK** button must be pressed. To cancel the deletion process the **Cancel** button shall be pressed.


REMARK! Alert will be deleted permanently.


3.6 Dashboard configuration

In order to configure dashboard settings the item **Dashboards** must be clicked in the **Configuration** window (*Picture 3*). The window for list of dashboards will be opened (*Picture 22*). Initially list is empty.



Picture 22. Window for list of dashboards.


In order to create a new dashboard the  icon must be pressed. The window for configuration of dashboard name will be opened (*Picture 23*).





Picture 23. Window for configuration of dashboard name.

Description of fields in name configuration window is available in *Table 15*.


Table 15. Description of fields in dashboard name configuration window.


Field	Description
Name	A short name for dashboard. Entry will be shown in the list column Name .
Description	Description of dashboard purpose. Entry will be shown in the list column Description .
Enable dashboard	Switch for enabling of dashboard after saving of the name configuration. By default switch is in the position  - enabled.

In order to save the configuration  button must be pressed. The window for the list of dashboard queries will be opened (*Picture 24*).



Picture 24. Window for the list of dashboard queries.

In order to configure a new dashboard query the  icon must be pressed. Configuration window will be opened (*Picture 25*).





Picture 25. Window for configuration of a dashboard query.

Description of the dashboard query configuration fields is available in the *Table 16*.

Table 16. Description of the dashboard configuration fields.

Field	Description
Name	Short name of a query. It will be used for identification of the query in the dashboard window.
Description	Description of the query.
Query	Query for triggering of the information refresh in the dashboard window.

Refresh time (s)	Time interval for refreshing of information appropriate to the query in dashboard window.
Query view	Specifies what information about query results must be displayed in the dashboard window. Available views are: <ul style="list-style-type: none"> - Time chart & List: the time chart and the list of log entries relevant to the query will be displayed; - List: only list of relevant entries will be displayed; - Time chart: only time chart with amount of log entries will be displayed.
Enable this query	Switch for enabling of the query immediately after saving of the settings. By default switch is in the position  - enabled.




In order to save configuration button  must be pressed. The window with the name of dashboard and list of queries will be opened. Example is shown in the *Picture 26*.



Picture 26. Example with list of queries.

Description of the dashboard fields is available in the *Table 17*.





Table 17. Description of the dashboard fields.

Field	Description
Name	Short name of the dashboard.
Description	Description of the dashboard.
Enable	Switch icon  identifies that dashboard is enabled and available in the main menu item Dashboards . In order to disable the dashboard the switch must be pressed. It will be shown as  and dashboard will be disabled.
Edit	By pressing on the icon  the dashboard name configuration window will be opened (<i>Picture 23</i>).


Description of columns in the list of queries is available in the *Table 18*.

Table 18. Description of the columns in the list of queries.

Column	Description
Name	Short name of the query.

Description	Description of the query.
Query	Query for search of information in the incoming log entries.
Refresh t.	Refresh time for search of query in the incoming data.
Enable	Switch for enabling or disabling of query. Switch icon  identifies that query is enabled. Switch icon  identifies that query is disabled.
Edit	Icon  for opening of query configuration window (<i>Picture 25</i>).
Remove	Icon  for deleting of query from the list.





By pressing the **Back to dashboards** GOL-GUI will return to list of dashboards. Example is shown in the *Picture 27*.



Picture 27. Example with list of dashboards.


Description of columns in the list of dashboards is available in *Table 19*.

Table 19. Description of columns in the list of dashboards.

Column	Description
Name	Short name of the dashboard. By clicking on the name the dashboard configuration window will be opened (<i>Picture 24</i>).
Description	Description of the dashboard.
Status	Switch for enabling or disabling of the dashboard. Switch icon  indicates that dashboard is enabled. Switch icon  indicates that dashboard is disabled and won't be available in main menu item Dashboards .
Edit	Icon  for opening of dashboard name configuration window (<i>Picture 23</i>).
Remove	Icon  for deleting of dashboard from the list.

3.7 Configuration of GOL general settings

In order to configure GOL general settings the item **General** must be pressed in the **Configuration** window (*Picture 3*). GOL general settings configuration window will be opened (*Picture 28*). Settings under **General** and **Storages** tabs have been configured during installation of GOL. In this chapter meaning of the settings is described and it is not recommended to change them.



Picture 28. GOL general settings configuration window.

Description of configuration tabs is available in *Table 20*.

Table 20. Description of configuration tabs.

Tab	Description
General	General settings for configuration of e-mail server.
Storages	golDB database settings.

3.7.1 Description of General tab settings

List with settings in **General tab** is available directly after opening of GOL general settings window (*Picture 28*).

Description of settings in **General** tab is available in *Table 21*.

Table 21. Description of settings in the **General** tab.

Settings	Description
System name	GOL system name. Should not be changed.
System E-mail	GOL system e-mail address. Address had been specified during GOL installation. Should not be changed.

3.7.2 Description of Storages tab settings

Storages tab contains golDB database settings that are necessary for connection of golLoader to the database (*Picture 29*). The settings in the tab have been configured during installation of GOL and they should not be changed later.

General configuration [Back to configuration](#)

General
Storages
Labels
Labels_d

golcfg
Golcfg can only be edited in the configuration file.

Address:	192.168.31.153
Protocol:	tcp
Port:	5550
Storage:	golcfg
Username:	root
Password:	root123

golstat

Address:	192.168.31.153	
Protocol:	tcp	
Port:	5550	
Storage:	golstat	
Username:	root	
Password:	root123	

Picture 29. golDB settings window.

All the golDB database instances have same settings which description is available in the Table 22.


Table 22. Description of golDB database settings.

Setting	Description
Address	golDB IP address. Should not be changed.
Protocol	Data exchange protocol that is used for communication with agents. Should not be changed.
Port	Port for connection to database. Should not be changed.
Storage	Name of golDB database instance. GOL is using following databases: <ul style="list-style-type: none"> golDB: database instance with consolidated log entries;

	<ul style="list-style-type: none"> • golcfg: database instance with GOL settings; • golstat: supports the work of dashboards, analytics and alerts. <p>Cannot be changed.</p>
Username	User name for golLoader connection to the database. Should not be changed.
Password	Password for golLoader and WinGol connection to the database. Should not be changed.

3.8 Configuration of GOL users

GOL user configuration can be performed in the **Users** section of general settings configuration window (*Picture 3*). By clicking on the sections name the window with registered GOL users will be opened. Example is shown in the *Picture 30*.








Picture 30. Example with list of GOL users.

List of users has two tabs:

- **Users (x)**. List with enabled and disabled GOL users;
- **Removed users (x)**. List with deleted users.

Index **(x)** identifies the amount of entries in each tab. Description of columns in users list is available in the *Table 23*.

Table 23. Description of columns in the users list.

Column	Description
Name	User name with which it is logging into GOL.
Code	Internal GOL code assigned to the user in golDB.
Description	Description of the user.
Level	Level of rights assigned to the user.
Status	Switch specifies is the GOL user enabled or disabled. Switch in the position  specifies that user is enabled and can access the GOL. Switch in position  specifies that user is disabled and cannot access GOL.
Edit	Icon  for configuration of user settings.
Remove	Icon  for deleting of user from the list.
	Icon for adding new user.

Immediately after installation of GOL there is only one user – *Administrator*. If it is intended that other users will use GOL, than it is necessary to add them to user list.

3.8.1 GOL user types and rights


There are three types of users in GOL – *Administrator*, *Manager* and *User*. User rights are related to GOL configuration possibilities. The user rights according the type of user are available in *Table 24*. With „X“ the rights available to each user are marked.

Table 24. Configuration rights available to each user type.

User type	Available GOL configuration items							
	My profile	Change password	Hosts	Alerts	Dashboards	General	Users	Source types
Administrator	X	X	X	X	X	X	X	X
Manager	X	X	X	X	X			
User	X	X						

3.8.2 Adding of new GOL user


In order to add new user in the window (*Picture 30*) with list of users' icon  must be pressed. The window for entering of user settings will be opened (*Picture 31*).



Picture 31. Using settings configuration window.


Description of user settings is available in *Table 25*.

Table 25. Description of user settings.

Field	Description
Name	Username for logging in to GOL.
Description	Description of the user.
Level	Dropdown list for assigning of user type. Available types must be chosen from the menu by pressing  icon.
E-mail	Users e-mail address.
Password	Password for logging in to GOL.

Enable user	The switch indicates whether the user immediately after creation in the system will be enabled or not. By default switch position is in position - enabled.
-------------	---

In order to save the settings button  must be pressed. The window with summary of user settings will be opened. Example is shown in the *Picture 32*.





Picture 32. Summary of user settings.

The description of items in user summary window is available in the *Table 26*.


Table 26. Description of items in user summary window.

Item	Description
Name	Username for authorization in GOL.
Description	Description of user.
Level	Access level assigned to the user.
E-mail	Users e-mail address.
Enable	The switch indicates whether the user immediately after creation in the system will be enabled or not. By default switch position is enabled.


If it is necessary to change user settings the icon  must be pressed. In order to accept the created settings the button  can be pressed or link **Back to users** clicked.

3.8.3 Change of user settings and deleting of users

GOL user settings can be changed in the window with users list (*Picture 30*). Available operations are:

- Activation or deactivation of user by pressing the **Status** switch.
- Changing of user settings by pressing icon . The window with user settings will be opened (*Picture 31*), where necessary changes can be made (described in the chapter 3.8.2 *Adding of new GOL user*).

- Deleting of the user by pressing the icon . The dialog for confirmation of deleting will be opened (*Picture 33*).






Picture 33. Dialog for confirmation of user deletion.

For deleting of the user button **OK** must be pressed. Button **Cancel** will cancel the request for user deletion.

Users from GOL are not really deleted, because golDB stores the actions they had performed in GOL. Deleted users are moved to **Removed users (x)** tab. Example is shown in the *Picture 34*.



Picture 34. List with deleted users.

In order to enable user again switch from position  must be moved to position  by pressing on it. The user settings can be changed by pressing icon .